ROLL-UP ORGANIZER

Finishes to approx. $8" \times 20"$

Please Note-----

All seams are ¹/₄" WOF = Width of Fabric

REQUIRED MATERIALS

- $8\frac{1}{2}$ " × 20 $\frac{1}{2}$ " (or a Fat 8th) for **outside**
- $8\frac{1}{2}$ " × 20¹/₂" (or a Fat 8th) for **inside**
- $5" \times 20\frac{1}{2}"$ (or a $\frac{1}{6}$ yard) for **pocket**
- (1) 20¹/₂" length and (1) 8" length (or ⁷/₈ yard) elastic
- 8" × 20" (or ¹/₄ yard) fusible interfacing (20" wide)

RECOMMENDED PRODUCTS

- Olfa 45mm Rotary Cutter
- Creative Grids 6¹/₂" × 24¹/₂" Ruler #CGR24
- Clover Hot Press Ruler
- Clover Flower Head Pins
- Clover Point 2 Point Turner
 - All available at Shabby Fabrics.com

CUT FABRICS

From Fabric A, cut:

• (1) $8\frac{1}{2}$ " × 20¹/₂" rectangle for **outside**

From Fabric B, cut:

• (1) $8\frac{1}{2}$ " × 20 $\frac{1}{2}$ " rectangle for **inside**

From Fabric C, cut:

• (1) $5'' \times 20\frac{1}{2}''$ rectangle for **pocket**

From **fusible interfacing**, cut:

• (1) 8" × 20" rectangle

From **elastic**, cut:

- (1) 20¹/₂" length
- (1) 8" length

FUSE INTERFACING


Fuse **interfacing** to wrong side of **Fabric A**, leaving a ¹/₄" seam allowance on all sides. (This will reduce bulk at the seams, making it easier to turn.)

This is your organizer outside. Set aside for a later step.



Shop for *beautiful colors* of soft, stretchy, banded elastic at Shabby Fabrics.com!





Organizer Outside (fused with interfacing)

ShabbyFabrics.com

PREPARE POCKET_

Choose one long edge of **Fabric C** to be the "top" of the pocket. Fold and press this long edge under $\frac{1}{4}$ " and press. Fold under another $\frac{1}{4}$ " and press. Top stitch to create a finished edge for your pocket.

Place pocket fabric, right side up, on top of **Fabric B**, right side up, aligning raw edges on sides and bottom. Baste along raw edges with a ¹/₈" seam allowance.

This is your organizer inside.

Add Elastic_____

Using a temporary marking pen, draw a line 2¹/₂" from top edge of organizer inside.

Align 201/2" length of **elastic** along this line. Tack both ends of elastic $\frac{1}{8}$ " from raw edges.

Fold 8" length of elastic in half to form a loop. (Be sure there are no twists in the elastic.) Place loop halfway between drawn line and top edge of pocket, aligning raw ends with raw edge of organizer inside. Tack elastic ½" from raw edge. *We recommend pinning loop against fabric to keep it from being sewn into the seam in the next step.*

Assemble Organizer_____

Place organizer outside on top of organizer inside, right sides together. Pin well. Sew around all four sides, leaving a 6" opening on the bottom side. Clip corners.

Turn right side out, and use point turner to push out corners.

Fold and press opening under 1/4".

Top stitch around entire organizer, moving elastic out of the way as needed.


Press. If you used a marking pen that erases with heat, avoid the area where you drew the line. If it disappears, you can remark it, this time $2\frac{1}{4}$ " from top edge.

Add Pocket Partitions___


Mark partitions at various desired widths. We recommend securing the elastic with pins to keep it in place along the traced horizontal line during this step.

Sew partitions from bottom to top, being careful not to catch elastic in presser foot.


Roll up organizer, and wrap looped elastic around roll to secure.



Organizer Inside







We'd love to see your finished Roll-Up Organizer! Share your photos on Facebook or Instagram and tag with **#SFRollUpOrganizer**

ROLL-UP ORGANIZER - page 2

Shabby Fabrics.com